

# RHEL: Extending a vmdk (Virtual Machine disk)

Article Number: 64 | Rating: Unrated | Last Updated: Sun, May 27, 2018 8:42 PM

# Tested on RHEL 5, 6 & 7

# This procedure may be carried out to make visible the new size of a disk that is already

# presented and used by the OS and that has been extended at virtual server level.

# Whenever possible I recommend to create a new disk instead of doing an extension. In

# some situations we may experience some trouble when trying to read the new size of the

# disk so a reboot may be needed.

# For RHEL under 5.3, if disk is being used by LVM and if it's already assigned to a Volume

# Group, a reboot of the server may be required in order to make visible the new size of the

# disk. Otherwise, as a workaround, one can add a new disk to the Volume Group and, then,

# 'pvmove' the physical extends to the new disk in order to free the old one.

# For RHEL 5.3 and higher

# Rescan device

**SD=<sd<**

```
echo 1 > /sys/block/$SD/device/rescan
```

```
# At this point, physical volume and disk sizes shown by 'pvdisplay'  
and 'fdisk' should be  
# different.
```

```
# If existing physical volume was created directly on the whole disk,  
without partition,  
# a 'pvresize' should be enough for the new size to be taken into  
account
```

```
pvresize /dev/$SD
```

```
# If, on the other hand, disk is already partitioned, this is, we are  
using devices in the  
# form /dev/sdx1, /dev/sdx2, we have to create a new partition with  
'fdisk' tool
```

```
fdisk /dev/$SD
```

```
The number of cylinders for this disk is set to 2480.
```

```
There is nothing wrong with that, but this is larger than 1024,  
and could in certain setups cause problems with:
```

- 1) software that runs at boot time (e.g., old versions of LILO)
- 2) booting and partitioning software from other OSs (e.g., DOS  
FDISK, OS/2 FDISK)

```
Command (m for help): p
```

```
Disk /dev/sdc: 20.4 GB, 20401094656 bytes
```

```
255 heads, 63 sectors/track, 2480 cylinders
```

```
Units = cylinders of 16065 * 512 = 8225280 bytes
```

Device	Boot	Start	End	Blocks	Id	System
/dev/sdc1	*	1	33	265041	83	Linux
/dev/sdc2		34	1958	15462562+	8e	Linux LVM

```
# Let's create a new partition. In our case, we'll create partition #
3
# (primary Linux LVM partition). For the first and last cylinder
usually default values
# will be ok; if not, choose carefully the beginning and the end of
the new partition
```

```
Command (m for help): n
```

```
Command action
```

```
e   extended
```

```
p   primary partition (1-4)
```

```
p
```

```
Partition number (1-4): 3
```

```
First cylinder (1959-2480, default 1959):
```

```
Using default value 1959
```

```
Last cylinder or +size or +sizeM or +sizeK (1959-2480, default
2480):
```

```
Using default value 2480
```

```
Command (m for help): t
```

```
Partition number (1-4): 3
```

```
Hex code (type L to list codes): 8e
```

```
Changed system type of partition 3 to 8e (Linux LVM)
```

```
Command (m for help): w
```

```
The partition table has been altered!
```

```
Calling ioctl() to re-read partition table.
```

```
WARNING: Re-reading the partition table failed with error 16:
Device or resource busy.
```

```
The kernel still uses the old table.
```

```
The new table will be used at the next reboot.
```

```
Syncing disks.
```

```
# Rescan disks
```

```
partprobe -s
```

```
# We may have an error like following one:
```

```
Warning: WARNING: the kernel failed to re-read the partition table on  
/dev/sdc (Device or resource busy).
```

```
As a result, it may not reflect all of your changes until after  
reboot.
```

```
# Then, use following command instead:
```

```
partx -a /dev/$SD
```

```
# New partition is ready to be used ('pvccreate', etc)
```

```
brw-r----- 1 root disk 8, 33 Nov  3 15:15 /dev/sdc1
```

Posted - Sun, May 27, 2018 8:42 PM. This article has been viewed 4046 times.

Online URL: <http://kb.ictbanking.net/article.php?id=64>