Installation of the Virtual I/O Server directly from the HMC

Article Number: 604 | Rating: Unrated | Last Updated: Tue, Jun 4, 2019 1:37 PM

Installation of the Virtual I/O Server directly from the HMC

HMC firmware version 7.7.7 allows installation of the Virtual I/O Server directly from the HMC.

Steps:

1.Download VIOS installation .iso images from IBM website.

2.Copy installation images to the HMC. Go to HMC Management – Manage Virtual I/O Server Image Repository

HMC Management (HMC Version)

Operations View Management Console Events	 View the event log of management consple operations and activities. 	
Shut Down or Restart Schedule Operations	Shut down or restart the management console Schedule selected operations for the management console	
Format Media Back up management console data Restore Management Console Data Save Upgrade Data	 Format a DVD, diskette, or USB flash memory device. Back up management console information to a remote system, or to a remote site Restore critical management console data from a remote source Save upgrade data to the management console hard drive or DVD 	
Change Network Settings Test Network Connectivity View Network Topology	 View current network information and change settings View network diagnostic information about the network protocols for the management console View and ping nodes within the management console's network topology 	
Tip of the Day View Licenses Change Default User Interface Settings Change User Interface Settings Change Date and Time Launch Guided Setup Wizard	 Display tips for using the console Read the licenses for the product Customize the default appearance of the management console user interface Customize the appearance of the management console user interface Change the date and time for the management console Step through setting up your management console users, passwords, network settings, and customer notification 	n of problems
Administration		
Change User Password Manage User Profiles and Access Manage Task and Resource Roles Manage Users and Tasks Manage Certificates Configure KDC Configure KDCP Remote Command Execution Remote Virtual Terminal Remote Operation	 Change your password Add, copy, remove, and modify management console system users and user profiles Add, copy, remove, and modify managed resource and task roles View the logged on users and the tasks they are running Create, modify, delete, and import certificates used on the Management Console, and view certificate signing information Key Distribution Center Configuration Enterprise Directory Service Configuration Enable or disable the command line interface on an management console Enable or disable virtual terminal connections for remotely connected management console sessions Control whether this management console can be operated using a web browser from a remote workstation 	
Change Language and Locale Create Welcome Text Manage Data Replication Manage Install Resources	 Change the management console user interface language and locale Customize the greeting displayed before logging on Share customizable data between management consoles including custom group data, customer information, and Add and remove operating environment install image resources on the management console 	l more
Manage Virtual I/O Server Image Repositor	Add and remove Virtual I/O Server install image resources on the HMC	Transferring

3.Complete information where the images can be copied from

a

📑 Import Virtua	al I/O Server Image
Name: * vio	os2234
Import From:	
Management Con	isole DVD
File System	
© Remote NFS S	erver
Remote FIP Se Remote CETD (erver
© Remote SFTP 3	
Remote Server:	* server.com
User Id:	* user
Password:	* •••••
Remote Directory	* /viosdir
Resource1:	* DVD 1 of 2 112014.iso
Resource2:	DVD 2 of 2 112014.iso
OK Cancel Hel	p
	omor Imago Bonository
Available Space:	13.60 GB
Import New Virtual I/	/O Server Image
Virtual I/O Server Im	ages:
Delete Edit	
Select Image Name	e Size
vios2234	4.91 GB
Close Help	

4. Select your brand new VIOS partition profile, and click **Operations – Activate – Profile** and select **Yes** for Install Virtual I/O Server as part of activation process?

Activate Logical Partition:viostest

Logical Partition name:

viostest

Install Virtual I/O Server as part of activation process?

Yes
 No

Select a profile below to activate the logical partition with.

Logical Partition profiles:



5. Type in the IP address, subnet mask and default gateway for VIOS.

Activate Logical Par viostest	tition - Install Virtual I/O Server -
Logical Partition Name:	viostest
Logical Partition Profile:	viostest
Select Virtual I/O Serve	r installation source
Local Repository DVD NIM Server	
Specify Virtual I/O Serv	er Values
NIM Server IP Address	* 165.72.131.86
Image:	* vios2234 Timport
Ethernet Adapter:	* U78C0.001.DBJN345-P2-C8-T3
IP Address:	* 165.72.54.21
Subnet Mask:	* 255.255.255.0
Gateway:	* 165.72.54.1
Advanced	
OK Cancel Help	

6. The installation process starts. It will do everything what is necessary to install the VIOS.

HMC console acts as a NIM server. Therefore, if the console is behind the firewall, you must ensure that all ports required by NIM are opened.

7. When the installation finished, open virtual terminal in the HMC *vtmenu*, and do the first login to the VIOS with a default password padmin for padmin user.

Once the VIOS is installed, you can use it as virtual media repository. It allows you to create virtual drive where you can load OS installation images (IBM i, AIX, or Linux) and proceed with OS installation completely remotely.

Posted - Tue, Jun 4, 2019 1:37 PM. This article has been viewed 21554 times.

Online URL: http://kb.ictbanking.net/article.php?id=604