

RHEL: Resize/disable /dev/shm filesystem

Article Number: 59 | Rating: Unrated | Last Updated: Sun, May 27, 2018 8:33 PM

Tested on RHEL 5, 6 & 7

Notes from www.walkernews.net, www.generation-linux.fr and Red Hat web site

Thanks to big memory size, nowadays most of RAM is not used at all. It is thus possible

to allocate a part of this physical memory to be used as storage.

The name given to a temporary unix file is '**tmpfs**'. From Linux 2.6 on this tmpfs is based

on ramfs. It is possible to fix a limit to its size in a way that system will allocate

memory dynamically.

By default, RHEL and most Linux distributions mount tmpfs (a RAM-based temporarily

filesystem for shared memory) on /dev/shm directory and this temporarily filesystem size

is always set to be **half of the installed memory**.

If that default size is not something expected, we can increase or reduce the /dev/shm

filesystem size.

We may drop or disable this temporarily RAM-based filesystem entirely, to prevent it

from auto-mount during system boot-up, if none of the application in our server is relying

on shared memory function or explicitly using tmpfs.

```

# Implementation
# -----
-----

# By default, tmpfs is mounted during system start-up and its
definition in /etc/fstab looks
# like this (on RHEL 7 there's no specification in /etc/fstab file by
default):

    tmpfs                /dev/shm                tmpfs
defaults                0 0

# What produces, for a system with 16 GB of RAM, a F.S. like this:

df -k
[... ]
tmpfs                7.8G    0 7.8G    0% /dev/shm

# Creating own tmpfs
# -----
-----

# Create a mount point on /mnt/mytmpfs.

mkdir /mnt/mytmpfs

# Change directory permissions so anyone will be able to
read/write/execute on it

chmod 777 /mnt/mytmpfs

# Finally, mount 'tmpfs' the usual way

```

```
mount -t tmpfs -o size=256M tmpfs /mnt/mytmpfs
```

```
# Remember that if we don't specify the size, it will be half the RAM.
```

```
# For this F.S. to be mounted during system boot-up, add it to /etc/fstab file:
```

```
tmpfs /mnt/mytmpfs tmpfs defaults,size=256M 0 0
```

```
# To increase or decrease /dev/shm filesystem size
```

```
# -----  
-----
```

```
# Open /etc/fstab and locate the line of /dev/shm and use the tmpfs size option to specify
```

```
# desired size (on RHEL 7, add the line if not present):
```

```
# e.g. 512MB:
```

```
tmpfs /dev/shm tmpfs  
defaults,size=512m 0 0
```

```
# e.g. 2GB:
```

```
tmpfs /dev/shm tmpfs  
defaults,size=2g 0 0
```

```
# To make change effective immediately, run following mount command to remount the
```

```
# /dev/shm filesystem:
```

```
mount -o remount /dev/shm
```

```
# Disabling /dev/shm filesystem
# -----
# -----

# Actually, Linux allocates the memory for this tmpfs on demand
basis, up to the maximum
# size shown in 'df -h' command output. If none of the application is
using the /dev/shm,
# this tmpfs in fact does not consume any memory space. So, why
disable it?

# Anyway, if you prefer to disable /dev/shm temporarily just execute
the umount command:

    umount /dev/shm

# To prevent tmpfs from auto-mount each time RHEL boots up, just
comment out or delete
# corresponding line from /etc/fstab.

# On RHEL 7 API file systems are mounted by systemd. As they
constitute an important mean of
# communication kernel<->userspace and userspace<->userspace they are
mounted automatically
# without user confirmation. It is possible to disable the automatic
mounting of some of them,
# but /dev/shm should always become available, so better leave it
mounted ;)
```

Posted - Sun, May 27, 2018 8:33 PM. This article has been viewed 14623 times.

Online URL: <http://kb.ictbanking.net/article.php?id=59>